

Upgrading Netmail Store with USB keys

Environment

Netmail Store

Synopsis

Use the procedure below to perform a rolling upgrade of the Netmail Store software version.

Solution

Please Read First!


1. *Once you have run through this upgrade procedure and restarted the nodes, you cannot backrev to the previous version.*
2. *Upgrading should avoid skipping a major version. If you are upgrading from a much older version, this should be done incrementally.*

Please follow the recommendations below for upgrading Store:

- *Version below 4.x upgrade to 4.x*
 - *Version 4.0.x - 5.0.x upgrade to 5.1.x*
 - *Version 5.1.x upgrade to 6.5.x*
 - *Above 6.x you can skip to 9.x*
3. *It is critical that the configuration on the USB key matches the IP of the server.*

Upgrade instructions:

1. Contact Netmail Support to obtain the download link for the new software version. Extract it to your computer. The contents should resemble:



2. Unplug the USB flash drive from one of the Store servers and plug connect it to a Windows computer. Make note of the drive letter assigned to the device (eg, X:).
3. Move the *license.txt* and *node.cfg* files from USB key to the computer (they are found in the */caringo* folder). **NB: This step is very important, as the next step will overwrite the config file and possibly**

the license file.

4. Copy all files from the new software package onto the USB flash drive. You will overwrite the existing files. **NB: There are hidden files and folders, so make sure you get everything. You may need to turn on the "show hidden files and folders" in Windows Explorer.**
5. Open a command prompt: Start Menu Run: "cmd.exe"
6. Run the *syslinux.exe* utility from the new package, passing the drive letter of the USB key as a parameter
eg, "D:\Download\StorePackage\syslinux.exe X:"
7. Move the *license.txt* and *node.cfg* files back to the USB key in the */caringo* folder.
8. Stop the USB flash drive and unmount. This is typically done by double-clicking the icon on the task bar that is labeled "Safely Remove Hardware" and the clicking the Stop button for the USB flash device. **NB : This is important to avoid corruption of the contents.**
9. Plug the USB flash device back into the Store node server and restart the server. Restarting the nodes should be done from the web console when ever possible (to do this you will need administrative credentials, which can be found in the *node.cfg* file of the USB key).
10. Monitor the admin console and ensure the server mounts correctly and has the new version number.

If you are doing a rolling upgrade of the nodes, it is recommended that you suspend volume recovery temporarily until all systems are up and running the same version of software. To do this, from the web console, click **Settings** and check **Suspend Volume Recovery**.

Notes

In the majority of cases a Netmail Archive system will be pointing to a particular node for all its activity. Netmail Archive jobs as well as end-user access will not be affected until this node is restarted. Regardless, it is highly recommended that no jobs be running when that node is restarted. Netmail Client Access services may also need to be restarted after the upgrade.

Help us improve!

Is this article helpful?	Yes No
Is it well written?	Yes No
Is the content complete?	Yes No